

電郵設定更新指南

VPS 郵件伺服器遷移 | 速查與圖文操作步驟

請在每部使用電郵程式的電腦、手機或平板上，更新現有帳戶的接收郵件伺服器名稱。電郵地址、Username、Password、SMTP outgoing server、Port 及加密設定全部保持不變。

What changes

The incoming server changes on each device you use for email.

OLD INCOMING SERVER

wowvps.dmbiz.net



NEW INCOMING SERVER

wowvps2.dmbiz.net

Keep your email address, username, password, account type and outgoing SMTP settings.

一頁速查

使用方式	需要做甚麼
POP 電郵程式	只把現有帳戶的 Incoming POP server 改為 wowvps2.dmbiz.net。
Webmail 網頁郵箱	開啟 https://wowvps2.dmbiz.net:2096 ，以原有帳戶資料登入。

舊接收伺服器：wowvps.dmbiz.net。新接收伺服器：wowvps2.dmbiz.net。不要新增或刪除電郵帳戶，也不要刪除舊郵件；POP 郵件可能只儲存在原本的裝置。

Webmail 登入

Webmail in a browser

Representative mockup - use your existing email address and password.

Browser address bar

<https://wowvps2.dmbiz.net:2096>


Sign in with your existing full email address and password.



1. 在瀏覽器輸入 <https://wowvps2.dmbiz.net:2096>。
2. 使用原有完整電郵地址及 Password 登入。

Windows 傳統版 Microsoft Outlook


以下適用於 Windows 傳統版 Outlook。新版 Outlook 的版面和手動修改伺服器方式可能不同；使用新版 Outlook 的客戶可向電郵技術支援查詢其版本的操作位置。



1. 開啟傳統版 Outlook，選擇 File > Account Settings > Account Settings。
2. 選取現有電郵帳戶，然後按 Change 或 Server Settings；名稱視乎 Outlook 版本。
3. 在 Incoming mail 欄位，把舊伺服器名稱改為 wowvps2.dmbiz.net。
4. Username、Password、SMTP outgoing server、Port 及加密設定保持不變。按 Next、Done 或 Finish 儲存。
5. 返回收件匣收取郵件，並向自己寄一封測試電郵。

macOS Apple Mail


以下適用於 Apple Mail 內現有的電郵帳戶；介面可能因 macOS 版本而稍有不同。



1. 開啟 Mail，選擇 Mail > Settings > Accounts。
2. 在左邊選取現有電郵帳戶，再開啟 Server Settings。
3. 在 Incoming Mail Server 的 Host Name 欄位輸入 wowvps2.dmbiz.net。
4. Username、Password、SMTP outgoing server、Port 及 TLS/SSL 設定保持不變。按 Save 儲存。
5. 返回收件匣重新收取郵件，並向自己寄一封測試電郵。

iPhone 和 iPad 內置 Mail

現行 iOS 路徑一般為 Settings > Apps > Mail > Mail Accounts；部分舊版本可直接在 Settings 找到 Mail。




1. 開啟 Settings > Apps > Mail > Mail Accounts，選取現有電郵帳戶。
2. 進入帳戶設定，在 Incoming Mail Server 下找到 Host Name，改為 wowvps2.dmbiz.net。
3. Username、Password、SMTP outgoing server、Port 及 SSL 設定保持不變。
4. 按 Done 或 Save 儲存，再開啟 Mail 收取郵件，並向自己寄一封測試電郵。

Android 電郵程式


Gmail app

以下適用於已加入 Gmail app 的現有非 Gmail 電郵帳戶；選單名稱可能因版本而不同。



1. 開啟 Gmail，按 Menu > Settings，再選取現有電郵帳戶。
2. 在 Server Settings 開啟 Incoming settings，把 Server 改為 wowvps2.dmbiz.net。
3. Username、Password、SMTP outgoing server、Port 及安全設定保持不變。儲存後收取郵件測試。

Samsung Email



1. 開啟 Email，按 Menu > Settings，選取現有帳戶，再開啟 Server settings 或 Incoming server。
2. 只把接收伺服器名稱改為 wowvps2.dmbiz.net；Username、Password、SMTP outgoing server、Port 及安全設定保持不變。
3. 按 Done 或 Save 儲存，重新收取郵件，並向自己寄一封測試電郵。

所有圖片均為示意畫面，不含真實客戶資料。電郵程式的選單名稱可能因版本而稍有不同。

Email Settings Update Guide

VPS mail server move | Quick reference and illustrated instructions

Update the incoming server name in the existing account on every computer, phone or tablet you use for email. Your email address, Username, Password, SMTP outgoing server, Port and encryption settings all stay unchanged.

What changes

The incoming server changes on each device you use for email.

OLD INCOMING SERVER

wowvps.dmbiz.net



NEW INCOMING SERVER

wowvps2.dmbiz.net

Keep your email address, username, password, account type and outgoing SMTP settings.

One page quick reference

How you access mail	What to do
POP email app	Change only the incoming POP server in your existing account to wowvps.dmbiz.net.
Webmail	Open https://wowvps2.dmbiz.net:2096 and sign in with your existing details.

Old incoming server: wowvps.dmbiz.net. New incoming server: wowvps2.dmbiz.net. Do not add or delete an email account, and do not delete old mail. POP messages may be stored only on the original device.

Webmail sign in

Webmail in a browser

Representative mockup - use your existing email address and password.

Browser address bar

<https://wowvps2.dmbiz.net:2096>


Sign in with your existing full email address and password.



1. Enter <https://wowvps2.dmbiz.net:2096> in your browser address bar.
2. Sign in using your existing full email address and Password.

Microsoft Outlook classic on Windows


These steps are for classic Outlook for Windows. New Outlook has a different interface and its manual server edit may differ; ask email support for the path in that version.



1. Open classic Outlook. Choose File > Account Settings > Account Settings.
2. Select your existing email account, then choose Change or Server Settings, depending on your version.
3. Under Incoming mail, replace the old server name with wowvps2.dmbiz.net.
4. Leave Username, Password, SMTP outgoing server, Port and encryption settings unchanged. Choose Next, Done or Finish to save.
5. Refresh your inbox and send yourself a short test email.

Apple Mail on macOS


These steps apply to an existing account in Apple Mail. The interface may vary slightly by macOS version.



1. Open Mail. Choose Mail > Settings > Accounts.
2. Select your existing email account on the left, then open Server Settings.
3. In Incoming Mail Server, set Host Name to wowvps2.dmbiz.net.
4. Leave Username, Password, SMTP outgoing server, Port and TLS/SSL settings unchanged. Choose Save.
5. Refresh your inbox and send yourself a short test email.

iPhone and iPad Mail

On current iOS versions, the path is usually Settings > Apps > Mail > Mail Accounts. On some earlier versions, Mail appears directly in Settings.




1. Open Settings > Apps > Mail > Mail Accounts. Select your existing email account.
2. In the account settings, find Host Name under Incoming Mail Server and enter wowvps2.dmbiz.net.
3. Leave Username, Password, SMTP outgoing server, Port and SSL settings unchanged.
4. Tap Done or Save, then open Mail, refresh your inbox and send yourself a short test email.

Android email apps


Gmail app

These steps are for an existing non-Gmail email account in the Gmail app. Menus may vary by version.



1. Open Gmail. Tap Menu > Settings and select your existing email account.
2. Under Server Settings, open Incoming settings. Change Server to wowvps2.dmbiz.net.
3. Leave Username, Password, SMTP outgoing server, Port and security settings unchanged. Save and refresh your inbox.

Samsung Email



1. Open Email. Tap Menu > Settings, select your existing account, then open Server settings or Incoming server.
2. Change only the incoming server name to wowvps2.dmbiz.net. Leave Username, Password, SMTP outgoing server, Port and security settings unchanged.
3. Tap Done or Save. Refresh your inbox and send yourself a short test email.

All images are representative mockups with no real customer information. Menu labels may vary slightly by app version.